

2024 CESM Tutorial

Intro to Lab: Simple XML Modifications

Hui Li Project Scientist II CGD, CCR

Aug 5-9, 2024

Outline

- Overview of model control files (env_*.xml files)
 - What are model control files
 - How to modify an env_*.xml file
- Controlling Run Length
 - Starting and Stopping a run
 - Restarting a Run
 - Changing Run Length
 - Using Timing Files
- Modifying the Type of Run
 - Hybrid, branch, startup
- Modifying Physics Timestep
- Exercise overview



What are model control files (*.xml)?

Yesterday, we learned the basic workflow of running your first CESM run:

- 1. Create New Case
- 2. Case Setup
- 3. Case Build
- 4. Case Submit

```
cases/b.day1.0> ls -1
archive metadata
Buildconf
case.build
case.cmpgen namelists
case.qstatus
case.setup
case.submit
check case
check input data
env archive.xml
env batch.xml
env build.xml
env case.xml
                          User Customizable case XML files
env mach pes.xml
env mach specific.xml
env run.xml
LockedFiles
pelayout
preview namelists
preview run
README.case
SourceMods
Tools
xmlchange
xmlquery
```

What are model control files (*.xml)?

- ❖ We control how we compile and run the model with *env_*.xml* files.
- ❖ These files are created with create_newcase.
- The most commonly used model control file is the "env_run.xml". We use this file to control the run length, run type, etc., based on our experiment design. We will practice this in today's lab session.

There are multiple env_*.xml files in the \$CASEROOT directory:

- env_archive.xml: specifies rules for short term archive script case.st_archive
- env_batch.xml: specifies batch specific settings used in case.submit script
- env_build.xml: specifies build information used in the case.build script
- env_case.xml: set by create_newcase and cannot be modified
- env_mach_pes.xml: specifies PE layout on NCAR HPC for components and used by case.run script
- env_mach_specific.xml: specifies machine specific information used in case.build script
- env_run.xml: sets run time information (such as length of run, number of submissions, ...)

How to modify and search env_*.xml files?

Editing:

When modifying "xml" files, we **highly recommend** using the tool, **xmlchange.** However, the user is free to use their editor of choice, i.e. **vi or emacs.**

Evaluate your understanding

If you want to manually resubmit an initial case that previously had a **CONTINUE_RUN** value of **FALSE**, how do you change it to **TRUE**?

▼ Click here for the solution

Use xmlchange to modify the variable value with the command:

./xmlchange CONTINUE_RUN=TRUE

How to modify and search env_*.xml files?

Searching:

To find xml variables in your case directory, we recommend usng the tool xmlquery. Note: You need to be in your case directory to execute these commands.

For example, to find out the run type of your job, search for xml variable RUN_TYPE:

```
./xmlquery RUN_TYPE
```

This will return the default RUN_TYPE value:

```
RUN_TYPE: hybrid
```

```
For help, type ./xmlchange --help type ./xmlquery --help
```

- ❖ The length of your model run is controlled by several run time variables in the env_run.xml file. These variables may be modified at the initialization of the model run and during the course of the model run.
- We will learn about customizing runtime settings to control starting, stopping, restarting and continuing a model run, and practice how to specify the run length of your long simulations.

Set runtime limits with STOP_OPTION and STOP_N

Run length options can be set using **STOP_OPTION** and **STOP_N** variables in env_run.xml.

- STOP_OPTION ==> sets the run length time interval type, i.e. nmonths, ndays, nyears.
- **STOP_N** ==> sets the number of intervals (set by STOP_OPTION) to run the model during each submission within the specified wallclock time.

For example:

If you want to run a simulation for 6 months during the job submission, you will need to set:

```
./xmlchange STOP_N=6
./xmlchange STOP_OPTION='nmonths'
```

Note: STOP_N and STOP_OPTION control the length of the run **per job submission**. A typical simulation is comprised of many job submissions. This is because you can only stay in the computer queue for a limited time.

Continue a run

Important concepts: "Initial run" and "continue run"

When a CESM model run is first initialized, it is called an initial run.

The variable **CONTINUE_RUN** in env_run.xml is a flag indicating if the current model run is an "initial run" or a "continue run".

- > For an initial run, CONTINUE_RUN must be set to FALSE
- ➤ If the model continues a run, CONTINUE RUN is set to TRUE

For example, say we submitted our initial job with CONTINUE_RUN = FALSE (because it was just initialized). If the run has been finished and everything looks good, and we want to continue the run for another month, what do we do?

We will need to use xmlchange to change **CONTINUE_RUN** = **TRUE** and submit the run again to carry on running the model. The model will use the restart files to continue our run with a bit-for-bit match as if it had never been stopped.

Setting run length for long simulations

Number of submissions and run length

- Recall that we can use STOP_N and STOP_OPTION to control the run length of each batch job submission.
- A typical long model simulation (say you want to run the model for 100 years) is comprised of many job submissions. This is because we have limited batch wallclock time for each job submission. For example, on Derecho, the regular queue wallclock limit is 12 hours.
- We can specify the number of times to resubmit the run using the RESUBMIT variable in env_run.xml to complete the long run.

Note: If RESUBMIT > 0, your scripts will automatically change CONTINUE_RUN = TRUE after completion of the first submission for all subsequent submissions into the queue.

Setting run length for long simulations

Question:

The tutorial version of the CESM model on Derecho simulates ~10 model years per wallclock day. The maximum wallclock request is 12 hours. If you want to run the model for 100 years, what values should be set for STOP_OPTION, STOP_N and RESUBMIT?

Answer:

Assume we want to use the full 12 hours for each job submission.

The model runs 10 years / wallclock day, which means that 12 hours would give us 5 years per job submission.

STOP_OPTION = nyears, STOP_N = 5, RESUBMIT = 19

Initial run of 5yrs + (19 resubmits * 5 years per job) = 100 years

Modifying the type of run using env_run.xml

CESM has three "types" of initial runs:

<u>STARTUP</u>: All model components are initialized from basic default initial conditions. The coupler

does NOT need an initial file.

HYBRID: - The atmosphere is initialized from initial condition files generated by a user-

specified CESM simulation

- The land, runoff, ocean and ice are initialized from restart files generated by a user-

specified CESM simulation.

- No coupler file is needed

- Initial conditions and restart files use the same reference case and reference date.

BRANCH: All model components are initialized from restart files generated by a user-specified

CESM simulation.

Modifying the type of run using env_run.xml

- > The xml variable *RUN_TYPE* determines the initialization type.
- Note that the RUN_TYPE setting is only important for the initial run of a production run when the CONTINUE_RUN variable is set to FALSE.
- ➤ After the initial run, the CONTINUE_RUN variable is set to TRUE, and the model restarts exactly using input files in a case, date, and bit-for-bit continuous fashion.

☐ For runs that are initialized as hybrid or branch runs, we will need restart/initial files from previous model runs (as specified by the variables, \$RUN_REFCASE and \$RUN_REFDATE). See the tutorial material for more details!

Exercise overview

In today's lab session, we will do three exercises to better understand xml modifications.

- ➤ In Exercise 1, we will practice runtime variable modifications.
- ➤ In Exercise 2, we will create a "branch" run and modify the ocean coupling frequency.
- > In Exercise 3, we will create a hybrid run and modify the atmosphere physics timestep.

